

# Acer Liquid Upgrade Manual

## Requirements

- You will need a PC/NB with Windows XP 32-bit (Service Pack 2 or above), Windows Vista (32- or 64-bit) or Windows 7 (32- or 64-bit)


## Notes

- The update will erase all your personal information (including contacts stored in the phone) and any programs you have installed. Please back up all necessary data to
- ~~Before the update, the battery level is greater than 30%.~~




## Upgrading your phone's operating system

Step 1. Download the EUU (end user upgrade) file that you need. Unzip the EUU file and open the folder. Double click **setup.exe**.





Step 2. If Microsoft .Net Framework 2.0 or above version has not been installed on the PC/NB, the .Net Framework installation window will appear. Click **Accept** to install .Net Framework 2.0.





Step 3. Select the installation folder and click **Next**.




## Acer Liquid OS Update Notification




Step 4. Click **Next** to confirm the installation of Acer Liquid Tool.




Step 5. A warning message will pop up. Follow the instructions and then click **OK**.



Step 6. When the installation is finished, the Installation Complete window will pop up. Click **Close**.



Step 7. The EEU welcome page will be shown. Click **Next**.




Step 8. Connect your Acer Liquid smartphone to the PC/NB. After connecting, the smartphone's OS version will be displayed. Click **Next** to start the upgrade.



## Acer Liquid OS Update Notification



Step 9. A window will pop up to indicate that the upgrade is completed. Click **Finish** and disconnect the smartphone from the PC/NB.






## Appendix

If you encounter any problems while upgrading and fail to complete the process, follow the instructions below to retry the upgrade process.

There are two ways to retry the upgrade process. Follow the steps on the message window and then restart the upgrade process.

i.



ii.

